

# CS4450

## Computer Networks: Architecture and Protocols

### Lecture 7: Link Layer

#### CSMA/CD

#### “Why” Frames

#### “Why” Switched Ethernet

**Rachit Agarwal**



# Announcements

- **Problem set 2 solutions out today**
  - First four questions included in the first exam
- **Practice prelim released today**
  - Hard to “closely” reflect the actual exam, but should be close
  - Solutions released by Friday

# Goals for Today's Lecture

- **Dive deep into Link layer design**
  - Finish the core link layer protocol: CSMA/CD
  - Why Frames? — Implementing Link Layer on top of Physical Layer
  - Why Switched Ethernet? — Understanding scalability problems
- Next lecture: THE **Spanning Tree Protocol**

## **Recap from last lecture**

# Recap: Data Link Layer

- **Communication Medium**

- Point-to-point

- The high-level ideas discussed so far were for point-to-point

- **Broadcast**

- **Original design of Link layer protocols**

- **More recent versions have moved to point-to-point**

- Today, we will discuss why so!

- **Network Adapters (e.g., NIC — network interface card)**

- The hardware that connects a machine to the network

- Has a “name” — MAC (Medium access control) address



# Recap: Sharing a broadcast channel

- **Context: a shared broadcast channel**
  - Must avoid/handle having multiple sources speaking at once
  - Otherwise collisions lead to garbled data
  - Need **distributed algorithm** for sharing channel
  - Algorithm determines **when** and **which** source can transmit

**Questions?**

# Techniques for sharing a broadcast channel

- **Context: a shared broadcast channel**
  - Must avoid/handle having multiple sources speaking at once
  - Otherwise collisions lead to garbled data
  - Need **distributed algorithm** for sharing channel
  - Algorithm determines **when** and **which** source can transmit
- **Three classes of techniques**
  - **Frequency-division multiple access**: coordinated sharing in space
  - **Time-division multiple access**: coordinated sharing in time
  - **Random access**: uncoordinated sharing
    - Detect collisions, and if needed, recover from collisions
    - **Carrier Sense Multiple Access (CSMA)**



# Frequency-Division Multiple Access (FDMA)



- **Frequency sharing**
  - Divide the channel into **frequencies**
  - **Every source is assigned a subset of frequencies**
    - And transmits data only on its assigned frequency
- **Goods: no collisions**
- **Not-so-good:**
  - A source may have nothing to send (frequency wasted)
  - Interference may cause disruption
  - Hard to implement for wired networks
- Used in many wireless networks
  - E.g., radio

# Time-Division Multiple Access (TDMA)

- **Time sharing**
  - Divide time into **slots**
  - Divide data into **frames**
    - Such that a frame can be transmitted in one slot
  - **Every source is assigned a subset of slots**
    - And transmits a frame only in its assigned slot
- **Goods: no collisions**
- **Not-so-good: Underutilization of resources**
  - During a slot, a source may have nothing to send
  - When the source has something to send, wait for its slot

# Random Access

- **Bob Metcalfe:**
  - Xerox PARC
  - Visits Hawaii, and gets the idea
  - Shared wired medium



**Life lesson:**


**If you want to invent great things,  
go to Hawaii :-)**

# Link Layer (Media Access Control, or MAC) Protocol

- **When source has a frame to send**
  - Transmit at full bandwidth
  - No a priori coordination among nodes
- **Two or more transmitting sources => collision**
  - Frame lost
- **Link-layer protocol specifies:**
  - How to detect collision
  - How to recover from collisions

# CSMA (Carrier Sense Multiple Access)

- CSMA: **listen** before transmit
  - If channel sensed idle: transmit entire frame
  - If channel sensed busy: defer transmission
- Human analogy: don't interrupt others!
- Does this eliminate all collisions?
  - **No**, because of nonzero propagation delay
- Solution:
  - Include a **Collision Detection (CD)** mechanism
  - If a collision detected
    - Retransmit



# CSMA/CD (Carrier Sense Multiple Access, Collision Detection)

- CSMA/CD: carrier sensing
  - **Collisions detected within short time**
  - Colliding transmissions aborted, reducing wastage
- Collision detection easy in wired (broadcast) LANs
  - Compare transmitted and received signals
- Collision detection difficult in wireless LANs

**CSMA/CD**



# Once a collision is detected ...

- **When should the frame be retransmitted?**
- Immediately?
  - Every NIC would start sending immediately
  - Collision again!
- Take turns?
  - Back to time division multiplexing
  - Problem?
    - Underutilization


# CSMA/CD in one slide!

- **Carrier Sense: continuously listen to the channel**
  - If idle: start transmitting
  - If busy: wait until idle
- **Collision Detection: listen while transmitting**
  - No collision: transmission complete
  - Collision: abort transmission
- **When to retransmit?: exponential back off**
  - After collision, transmit after “waiting time”
  - After  $k$  collisions, choose “waiting time” from  $\{0, \dots, 2^k - 1\}$
  - Exponentially increasing waiting times
  - But also, exponentially larger success probability

# CSMA/CD—Exponential Back-off: An example



**Attempt 1: Suppose a collision happens**



**Attempt 2: Four possibilities**

**Success with Probability = 0.5**

**Questions?**

## **Group Exercise:**

**What is the success probability in attempt 3?**

**Answer: 0.75**

## **Why Frames?**

**(Layering: Link Layer on top of Physical Layer)**

# Building Link Layer on top of Physical Layer

- Physical layer sends/receives bits on a link, and forwards to link layer

- View at the destination side physical layer:

01010110011111101111101111100101000111

- Challenge: how to take the above bits and convert to:

01010110011111101111101111100101000111

- **Problem:** how does the link layer separate data into correct “chunks”?

- Chunks belonging to different applications

- Data link layer **interfaces** with **physical layer** using **frames**

- Implemented by the network adaptor

- **Finally: What are these frames?**






# Frames



# Identifying start/end of frames: Sentinel Bits

- Delineate frame with special “sentinel” bit pattern
  - e.g., **01111110** -> start, **01111111** -> end



- **Problem: what if the sentinel occurs within the frame?**
- Solution: **bit stuffing**
  - Sender always inserts a **0** after five **1s** in the frame content
  - Receiver always removes a **0** appearing after five **1s**

# When Receiver sees five 1s...



- If next bit is 0, remove it, and begin counting again
  - Because this must be a stuffed bit
  - we can't be at beginning/end of frame (those had six/seven 1s)
- If next bit is 1 (i.e., we have six 1s) then:
  - If following bit is 0, this is the start of the frame
    - Because the receiver has seen 01111110
  - If following bit is 1, this is the end of the frame
    - Because the receiver has seen 01111111

# Example: Sentinel Bits

- Original data, including start/end of frame:

01111110011111101111101111100101111111

- Sender rule: five 1s -> insert a 0


- After bit stuffing at the sender:

01111110011111010111110011111000101111111

- Receiver rule: five 1s and next bit 0 -> remove 0

01111110011111101111101111100101111111

# Ethernet “Frames”



- **Preamble:**
  - 7 bytes for clock synchronization
  - 1 byte to indicate start of the frame
- **Names:** 6 + 6 bytes (MAC names/addresses)
- **Protocol type:** 2 bytes, indicating higher layer protocol (e.g., IP)
- **Data payload:** max 1500 bytes, minimum 46 bytes
- **CRC:** 4 bytes for error detection

# What about source/destination Addresses?

- **Frames are at Layer-2**
  - Thus, use Layer-2 addresses (MAC names/addresses)
- **MAC address**
  - Numerical address associated with the network adapter
  - Flat namespace of 6 bytes (e.g., 00-15-C5-49-04-A9 in HEX)
  - Unique, hard coded in the adapter when it is built
- **Hierarchical Allocation**
  - **Blocks**: assigned to vendors (e.g., Dell) by IEEE
    - First 24 bits (e.g., 00-15-C5-\*\*-\*\*-\*\*)
  - **Adapter**: assigned by the vendor from its block
    - Last 24 bits

**Questions?**


**Putting it all together  
(Traditional Ethernet)**



# Traditional Ethernet

- **(Source) Link layer receives data from the network layer (more later)**
- **(Source) Link layer divides data into frames**
  - How does it know source/destination MAC names?
  - Source name is easy ... destination name is tricky (more later)
- **(Source) Link layer passes the frame to physical layer**
  - Frames up the frames (using sentinel bits)
  - **And broadcasts on the broadcast Ethernet**
- **(EACH) physical layer regenerates the frame...**
  - And sends it up to the (destination) link layer ....
    - Which sends the data to the network layer .... **If and only if:**
      - destination name matches the receiver's MAC name
      - Or, the destination name is the broadcast address (FF:FF:FF:FF:FF:FF)

# Traditional Ethernet



- Ethernet is “plug-n’play”
  - A new host plugs into the Ethernet is good to go
  - No configuration by users or network operators
  - Broadcast as a means of bootstrapping communication

# Performance of CSMA/CD

- **Time spent transmitting a frame (collision)**
  - Proportional to distance  $d$ ; why?
- **Time spent transmitting a frame (no collision)**
  - Frame length  $p$  divided by bandwidth  $b$
- **Rough estimate for efficiency (K some constant)**

$$E \sim \frac{\frac{p}{b}}{\frac{p}{b} + Kd}$$

- **Observations:**
  - For large frames AND small distances,  $E \sim 1$
  - **Right frame length depends on  $b$ ,  $K$ ,  $d$**
  - **As bandwidth increases,  $E$  decreases**
    - That is why high-speed LANs are switched

**Questions?**